Följ manualen för att stänga av certifieringen av drivrutiner i windows 8. Används för att installera exempel Citizen CT-S851



Börja med att föra musen upp till höger för att komma åt menyerna.

Tryck på 'Inställningar' eller 'Settings'



Välj 'Change PC Settings' eller 'Ändra datorinställningar'



Gå till 'General' eller 'Allmänt' → Scrolla längst ner till 'Advanced Start Up' eller 'Avancerad Start'. Tryck därefter på 'Restart now' eller 'Starta om nu'

	Language preferences	^
PC settings	Available storage	
Activate Windows	You have 64,9 GB available. See how much space your apps are using. View app sizes	
Personalise	Refresh your PC without affecting your files	
Users	If your PC isn't running well, you can refresh it without losing your photos, music, videos and other personal files.	
Notifications	Get started	
Search	Pomova overything and reinstall Windows	
Share	If you want to recycle your PC or completely start again, you can reset it to its	
General	factory settings. Get started	
Privacy		
Devices	Advanced start-up	
Devices Ease of Access	Advanced start-up Start up from a device or disc (such as a USB drive or DVD), change Windows start- up settings or restore Windows from a system image. This will restart your PC. Restart now	
Devices Ease of Access Sync your settings	Advanced start-up Start up from a device or disc (such as a USB drive or DVD), change Windows start- up settings or restore Windows from a system image. This will restart your PC. Restart now	
Devices Ease of Access Sync your settings	Advanced start-up Start up from a device or disc (such as a USB drive or DVD), change Windows start- up settings or restore Windows from a system image. This will restart your PC. Restart now	~
Devices Ease of Access Sync your settings	Advanced start-up Start up from a device or disc (such as a USB drive or DVD), change Windows start- up settings or restore Windows from a system image. This will restart your PC. Restart now	~

'Troubleshoot' eller 'Felsökning'

Choose an optior	i -
Exit and continue to Windows 8	
Refresh or reset your PC, or use advanced tools	
Turn off your PC	

'Advanced Options' eller 'Avancerade alternativ'

E	Trou	bleshoot
	÷.	Refresh your PC If your PC isn't running well, you can refresh it without losing your files
	Ó.	Reset your PC If you want to remove all of your files, you can reset your PC completely
	š≡	Advanced options

'Ta Start-Up-Settings' alternativt 'Startinställningar'

€ Adva	anced options	S		
	System Restore Use a restore point recorded on your PC to restore Windows	C:\	Command Prompt Use the Command Prompt for advanced troubleshooting	
	System Image Recovery Recover Windows using a specific system image file	\$	Start-up Settings Change Windows' start-up behaviour	
<o>></o>	Automatic Repair Fix problems that keep Windows from loading			

Tryck på 'Restar Now' eller 'Starta Om'

¢	Start-up Settings
	Restart to change Windows options such as: • Enable low-resolution video mode • Enable debugging mode • Enable boot logging • Enable Safe Mode • Disable driver signature enforcement • Disable early-launch anti-malware protection • Disable automatic restart on system failure
	Restart

Vid uppstart nu trycker man 7 på tangentbordet. 'Disable driver signature enforcement' eller på svenska 'Inaktivera krav på signering av drivrutin'.

Därefter kan skrivaren installeras utan problem!

Pres	is a number to choose from the options below:
	Use number keys or functions keys F1-F9
	ose number keys of functions keys (= 1.5.
	1) Enable debugging
	2) Enable boot logging
	3) Enable low-resolution video
	4) Enable Safe Mode
	5) Enable Safe Mode with Networking
	6) Enable Safe Mode with Command Prompt
	7) Disable driver signature enforcement
	8) Disable early launch anti-malware protection
	9) Disable automatic restart after failure
	Press F10 for more options
	Press Enter to return to your operating system